


G-Scan Update Procedure

1/. Go to www.gscan.com.au - click **MENU** button and select **Members Area** - enter your name & scan tool serial number and click **Log-In**

2/. Download latest version
e.g. **AU_AUG_2011.zip** - we recommend save to the Desktop



3/. When **DOWNLOAD** has finished, right click Desktop and from the drop down Menu select 'New' and then 'Folder'



Select & Rename the folder to something you will remember – our example shows Gscan_042011






Now select the downloaded zip file and drag 'n' drop the file into your named folder



4/. Open your named folder and right click the downloaded zip file


Select 'Extract Here' from the drop down Menu



The files will extracted from the zip file to the folder



Once files have been extracted into your folder, select the file named 'setup.exe' and install the latest PC Utility SW – the program **G-Scan PC Utility** will show July,2011 after installation





5/. Click the **G-Scan PC Util** desktop icon



to open the program

Click '**Software Update**' and follow the screen prompts, step by step - it is very easy to re-format the SD card and update file copying takes approximately 20 minutes



NOTE: During the G-Scan software update PC users may see a screen showing format selections - Please ensure that '**FAT32**' is selected and '**Quick Format**' is unchecked

6/. Re-insert SD card into G-Scan. Supply scan tool with external power as firmware will automatically update once your scan tool is switched on

7/. We recommend keeping your named Desktop G-Scan folder and the contents until completion of your next new G-Scan software download